

FIXEdge installation on Linux. Step by step instruction

- [Prerequisites and System Requirements](#)
- [Deployment of FIXEdge](#)
 - [FIXEdge Components](#)
 - [Steps to Install](#)
- [Troubleshooting](#)
 - [FIXICC doesn't connect to FIXICC agent](#)
 - [FIXICC agent doesn't start](#)
 - [FIXEdge doesn't start from FIXICC](#)
 - [FIXEdge doesn't start with 'FixEdge1.run.sh' script](#)
 - [FIXEdge cannot start with an incorrect or expired license](#)
 - [Binary files and shell scripts have no "executable" permissions](#)
 - [How to see if a specific port is used](#)
 - [Open FIXEdge ports using firewalld](#)

Prerequisites and System Requirements

1. Supported operating systems:
 - Linux RHEL/CentOS 6
 - Linux RHEL/CentOS 7
2. The list of packages that should be installed before FIXEdge's installation:
 - unzip
 - libtool-ltdl

java-1.7.0-openjdk

```
$ sudo yum install java-1.7.0-openjdk
```

To install them use the following commands with superuser permissions:

```
$ sudo yum install unzip  
$ sudo yum install libtool-ltdl
```

3. The list of ports that should be opened:
 - TCP: 8005, 8901, 8902, 8905.
 - UDP: 1234

Deployment of FIXEdge

FIXEdge Components

- FIXEdge-x.x.x.tar.gz
- engine.license
- fixicc-x.x.x.zip - this package is used for launching FIX Integrated Control Center on Windows PC

fixicc-linux-x.x.x.zip

fixaj2-license.bin

Steps to Install

 Expected packages are located in /home/user/downloads.

The installation assumes that FIXEdge will be installed in /home/user/B2BITS under user's home directory.

Create B2BITS directory:

```
$ cd /home/user/  
$ mkdir B2BITS
```

1. Unpack the FIXEdge-x.x.x.tar.gz archive:

```
$ tar xvf downloads/FIXEdge-x.x.x.tar.gz -C /home/user/B2BITS
```

2. Put the engine.license file into the FIXEdge's directory:

```
$ cp downloads/engine.license /home/user/B2BITS/FIXEdge/
```

3. Install FIXICC Agent daemon with sudo user rights:

```
$ cd /home/user/B2BITS/FIXEdge/fixicc-agent/bin/  
# ./installDaemon.sh
```

Start FIXICC Agent daemon:

```
$ ./startDaemonNoPriv.sh
```

It can take up to several minutes to start at the first time:

```
***** INSTALLING FIXICC_Agent_Server *****  
  
Jul 14, 2017 2:55:03 PM org.rzo.yajsw.os.posix.PosixService getPid  
INFO: wrapper pid file: /home/user/B2BITS/FIXEdge/fixicc-agent/logs/wrapper.FIXI  
Jul 14, 2017 2:55:04 PM org.rzo.yajsw.os.posix.PosixService install  
WARNING: created daemon script: /etc/rc.d/init.d/FIXICC_Agent_Server  
Jul 14, 2017 2:55:04 PM org.rzo.yajsw.os.posix.PosixService install  
INFO: error on creating script link ?unresolved?/S20FIXICC_Agent_Server  
Jul 14, 2017 2:55:04 PM org.rzo.yajsw.os.posix.PosixService install  
INFO: error on creating script link ?unresolved?/K20FIXICC_Agent_Server  
Service FIXICC Agent Server installed  
  
***** STARTING FIXICC_Agent_Server *****  
  
Service FIXICC_Agent_Server started  
  
Jul 14, 2017 2:57:46 PM org.rzo.yajsw.os.posix.PosixService getPid  
INFO: wrapper pid file: /home/user/B2BITS/FIXEdge/fixicc-agent/logs/wrapper.FIXICC_Agent_Server.pid  
Jul 14, 2017 2:57:48 PM org.rzo.yajsw.os.posix.PosixService getPid  
INFO: wrapper pid file: /home/user/B2BITS/FIXEdge/fixicc-agent/logs/wrapper.FIXICC_Agent_Server.pid  
Jul 14, 2017 2:57:48 PM org.rzo.yajsw.os.posix.PosixService getPid  
INFO: wrapper pid file: /home/user/B2BITS/FIXEdge/fixicc-agent/logs/wrapper.FIXICC_Agent_Server.pid  
Service FIXICC_Agent_Server started
```

4. Launch FIXICC on local (Linux) machine or on Windows PC (use the fixicc-x.x.x.zip package):

Linux

```
$ ./B2BITS/FIXEdge/fixicc/bin/fixicc
```

Windows


```
\\fixicc\\bin\\fixicc.exe
```

5. Use option 'Add Server' to add FIXEdge server with the following parameters:

Import the fixaj2-license.bin license in FIXICC GUI:
Help -> Import license...

```
Type: B2BITS FIX Edge  
Host: localhost (or host of the machine with FIXEdge)  
Port: 8005  
Username: admin  
Password: admin
```

6. Select 'Connect' option in the context menu of the created server.



7. Select 'Start Server' option in the context menu of the created server.

Please refer to [FIXICC User Guide](#) for detailed instructions.

Installation complete

See also:

[How to setup secure SSL/TLS conntion between FIXEdge, FIXICC-agent and FIXICC](#)

[How to change FIXICC Agent password](#)

Perform these steps instead step #2 of Installation.

1. Put license file (engine.license) into FIXEdge's root dir:

```
$ cp downloads/engine.license /home/user/B2BITS/FixEdge/v.5.8.0.x
```

2. Unpack fixicc-agent-2.x.x.zip into FIXEdge's root dir:

```
$ unzip downloads/fixicc-agent-2.x.x.zip -d /home/user/B2BITS/FixEdge/v.5.8.0.x
```

3. Put license file (fixaj2-license.bin) into FIXICC Agent conf dir (fixicc-agent/conf):

```
$ cp downloads/fixaj2-license.bin /home/user/B2BITS/FixEdge/v.5.8.0.x/fixicc-agent/conf
```

4. Configure paths to FIXEdge files in B2BITS/FixEdge/v.5.8.0.x/fixicc-agent/conf/agent.properties:

- ServerHome = ..
- StartFile = bin/FixEdge1.run.sh
- StopFile = bin/FixEdge1.stop.sh
- LogUrl = ../FixEdge1/log

Continue Installation from step #3.

Troubleshooting

FIXICC doesn't connect to FIXICC agent

1. Go to the /home/user/B2BITS/FIXEdge/fixicc-agent/logs directory and open fixicc-agent.log with any text editor.

a. Check if the following notes exist in the log:

```
INFO|13743/0|Service FIXICC - Agent Server|14-06-19 20:39:15|Agent is started successfully
INFO|13743/0|Service FIXICC - Agent Server|14-06-19 20:39:15|Agent started on port: 8005
```

b. If the notes are absent then go to the '[FIXICC agent doesn't start](#)' section.

2. Select the 'Edit Server' option in the context menu of the FIXEdge server in FIXICC.

3. Make sure that the value of the 'Port' and 'Host' in the 'Basic Settings' corresponds to the FIXICC Agent port and the host of the FIXEdge machine.

4. Make sure that all ports from the '[Prerequisites and system requirements](#)' section are opened and reachable by telnet from the remote host.

```
telnet <remote host> 8005
```

FIXICC agent doesn't start

1. Go to the /home/user/B2BITS/FIXEdge/fixicc-agent/logs directory and open fixicc-agent.log with any text editor.

2. Find the messages with [ERROR] and [FATAL] level. These messages are able to help with the understanding of the possible issues. If there is a requirement for technical assistance then contact the support team SupportFIXProducts@epam.com.

FIXEdge doesn't start from FIXICC

1. Go to the B2BITS/FIXEdge/bin directory and run FIXEdge:

```
$ cd /home/user/B2BITS/FIXEdge/bin
$ ./FixEdge1.run.sh
```

2. If the script was executed successfully then go to the /home/user/B2BITS/FIXEdge/fixicc-agent/logs directory and open fixicc-agent.log with any text editor (otherwise go to the '[FIXEdge doesn't start with 'FixEdge1.run.sh' script](#)' section).
3. Check if the following note exists in the log and make sure that the path presented below lead to the existing engine.properties file:

```
[UtilProperties] Properties load successful: /home/user/B2BITS/FIXEdge/fixicc-agent/./FIXEdge1/conf/engine.properties
```

4. If the note is absent find the messages with [ERROR] and [FATAL] level. These messages are able to help with understanding of the possible issues. If there is a requirement for technical assistance then contact the support team SupportFIXProducts@epam.com.

FIXEdge doesn't start with 'FixEdge1.run.sh' script

1. Go to the B2BITS/FIXEdge/FIXEdge1/log directory and open FixEdge.log with any text editor.
2. Find the messages with [ERROR] or [FATAL] level. These messages are able to help with understanding of the possible issues. If there is a requirement for technical assistance then contact the support team SupportFIXProducts@epam.com.

FIXEdge cannot start with an incorrect or expired license

1. Go to the B2BITS/FIXEdge/FIXEdge1/log directory and open FixEdge.log with any text editor.
 - a. Request a new license file from the sales team sales@btobits.com if the FixEdge.log file contains the following error:

```
ERROR [Engine] 140410078865152 License is expired - components will be stopped! Please contact us at SupportFIXAntenna@epam.com for further assistance.
```

- b. Make sure that the license file has a correct 'engine.license' name and placed in the root directory of FIXEdge if the FixEdge.log file contains the following error:

```
ERROR [FL_FixEngine] 140029176809248 Unable to initialize EngineAdaptor. Reason: Please check the FIX Engine's settings: Cannot open the file "/home/user/B2BITS/FIXEdge/bin/./engine.license" (the "LicenseFile" property). No such file or directory. (Error code = 2)
```

2. Restart FIXEdge after updating the license to apply the changes.

Binary files and shell scripts have no "executable" permissions

1. Set the permissions for the needed files with the following command:

```
$ chmod 755 /home/user/B2BITS/FIXEdge/fixicc-agent/bin/*
```

How to see if a specific port is used

To ensure that port 8005 is not used, using the [netstat](#) or the [ss](#) command.

```
netstat -na | grep :8005
ss -na | grep :8005
lsof -i:8005
```

If the output is blank, then the port is not currently used.

Open FIXEdge ports using firewall

In RHEL 7 the tool `firewall-cmd` is used for updating firewall rules.

1. The following commands open ports 8005, 8901, 8902, 8905, 1234. The superuser permissions are required in order to change the system settings.

```
sudo firewall-cmd --add-port=8005/tcp --permanent
sudo firewall-cmd --add-port=8901/tcp --permanent
sudo firewall-cmd --add-port=8902/tcp --permanent
sudo firewall-cmd --add-port=8905/tcp --permanent
sudo firewall-cmd --add-port=1234/udp --permanent
sudo firewall-cmd --reload
```

The flag `--permanent` is used to keep changes after the host reboot.

2. To verify the changes run the following command (superuser permissions are required)

```
sudo firewall-cmd --list-ports
```



In RHEL 6 ports should be open by modifying iptables.